

LogView Release Notes:

Version 5.9.9.0 Release date: April 28, 2011

- MP-4000 interpretation and new events supported.
 - Added support for CT and MTS.
 - Flags added to temperature log indicating MTS, CT, CA and Capacity limitation activity.
 - AFAM event is now completely implemented.
 - Fix to Interpretation of Batch Run Control is missing.
 - Fix to Humidity readout is wrong.
- Known issues
 - Viewing a Daikin log file retrieved with the LogManII device LogView may stop with a message "HandleTripAndUSDALog" "Division by zero". A workaround for the issue is to use LogView version 2.9.2.0.

Version 5.9.8.0 Release date: January 11, 2011

- MP-4000 interpretation and new events supported.
 - Calibration event changed to show one decimal.
 - Pressure columns are changed for correct conversion BARr vs. PSI.
 - Set point rh/O2/Co2 added to temperature log.
- SG+ interpretation and alarm codes updated.
 - Alarm text added to engine restart event.
- MP-2000 / MP-3000 interpretation.
 - Pressure columns are changed for correct conversion BARr vs. PSI.
- Added support for additional Carrier event codes (82,83,84,85,89,90,91,92,96,98).
- Fix to Cold treatment report is not working if no USDA columns are available.

Version 5.9.7.1 Release date: May 26. 2010

- Minor bug fix. New trend curves in different colors.

Version 5.9.7.0 Release date: May 7. 2010

- Support of Star Care functionality in MCI Star Cool Reefer units.

Version 5.9.6.0 Release date: January 28. 2010

- Last used LogMan type saved as default for next time
- SG+ Interpretation updated
- MP-3000 Interpretation updated
- MP-4000 / Magnum Plus support
- DAIKIN Decos IIIe support

Version 5.9.5.0 Release date: Not released

Version 5.9.4.0 Release date: Not released

Version 5.9.3.0 Release date: Not released

Version 5.9.2.0 Release date: June 2. 2008

- New SG+ Events supported
 - Event Text changed – Engine stopped reason unknown
 - New Event – New software loaded
- Type of device connected stored. Next time LogView is opened the same type of device is defaulted

Version 5.9.1.0 Release date: February 20. 2008

- Support of LogMan II
- Interpretation of SG+ Controller for TK Gensets

Version 5.8.4.0 Release date: July 7. 2007

- MP-3000 Events added (AFAM - Manuel, Gas analyzer - Calibration, Gas analyzer - Calibration readout)
- Printout of Cold Treatment Report